

# C2000Ware MotorControl SDK InstaSPIN Universal GUI

## QUICK START GUIDE

---

A series of lab projects are available to help you evaluate InstaSPIN™-FOC solutions. The C2000Ware MotorControl SDK InstaSPIN Universal GUI allows you to instrument and interact with these projects over a JTAG connection.

This InstaSPIN Universal GUI supports:

- LAUNCHXL-F280049C LaunchPad with on-board XDS110 debug probe
- TMDSCNCD280049C controlCARD with on-board XDS100v2 debug probe
- Any InstaSPIN-enabled F28004x device on custom hardware with a JTAG connection

## Contents

1	Installation .....	2
2	Hardware setup .....	2
3	Using the GUI .....	3
3.1	Create a binary .....	3
3.2	Configuring the GUI.....	3
3.3	Running the GUI .....	5
3.3.1	GUI connection .....	5
3.3.2	Launching the GUI.....	5
3.3.3	GUI overview .....	6
3.3.4	Motor ID lab example .....	7
4	Next steps .....	9
5	Support .....	10

## 1 Installation

The InstaSPIN Universal GUI is available in the TI Cloud Tools Gallery and can be run in your web browser without any installation of the application itself. As you follow the steps outlined in this document, dev.ti.com may prompt you to install tools as needed—such as the TI Cloud Agent to allow your browser to connect to your board device or the GUI Composer Runtime to allow you to run the GUI standalone on your desktop. Perform these installations as requested, following the instructions on the site.

## 2 Hardware setup

Please review the quick start or hardware guides for your particular controlCARD, LaunchPad, and/or motor drive kit (that is available in the MotorControl SDK) for details of hardware setup, including jumper and switch settings.

## 3 Using the GUI

The InstaSPIN Universal GUI is available in the [TI Cloud Tools Gallery](#) (Chrome is the preferred browser). Type “InstaSPIN” into the search box and hit enter. You should see the “C2000Ware MotorControl SDK InstaSPIN GUI” in the search results.

Clicking the GUI image will launch the application in your browser. **However**, by default, the GUI is configured to load and run a .out for the LAUNCHXL-F280049C with a BOOSTXL-DRV8320RS with default user.h parameters. As this is a very specific configuration, you should complete the following steps to run the application instead.

### 3.1 Create a binary

The Universal GUI allows you to instrument variables that exist in a .out file that the GUI will load and run. Variables that you will interact with primarily reside in the userParams and motorVars structures (declared in the main.c of most InstaSPIN labs). You will need to make sure that the variables with which you want to interact are compiled into your .out. Also, be aware that even though a variable may exist in these structures, changing the variable in the GUI may have no effect if it is not “get” or “set” in the application being run.

To start, it is best to use a .out from an InstaSPIN lab project from the MotorControl SDK. If you are new to InstaSPIN and CCS, start with the **MotorControl SDK InstaSPIN Lab Guide** found in the `\solutions\common\sensorless_foc\docs\labs` directory of the SDK. It will give you an introduction to the labs’ functionality, how to import them into CCS, how to customize the code for your motor, and how to build the .out. This document will use the InstaSPIN Motor ID lab (is05\_motor\_id) for its examples.

**It is recommended that you use the Flash\_Lib build configuration.**

Once you have built your project, locate the .out in your workspace. You will need it for the following steps.

### 3.2 Configuring the GUI


From the aforementioned TI Cloud Tools Gallery search result page, click the “Import to GUI Composer” icon for the Universal GUI.



**Figure 1** - Red box highlights the “Import to GUI Composer” icon in the Gallery.

You should now see **C2000Ware\_MotorControlSDK\_InstaSPIN\_GUI** in your GUI Composer projects list, and the front tab of the Universal GUI in the main panel.


# TI Spins Motors



**Figure 2** - View of the GUI Composer project workspace with the Universal GUI imported.

To configure your connection settings and .out, go to “Project”->”Properties...” Leave the first page of properties as it is and hit “Next.” You should see the Target Programming page where you can select your Device, Connection, and Executable. Go ahead and make the appropriate selections for your kit, uploading the .out generated in the previous section for the Executable.

For example, if you are using the TMDSCNCD280049C controlCARD with on-board XDS100v2 debug probe, you would change the Connection box to “Texas Instruments XDS100v2 USB Debug Probe” and upload the .out for an appropriate lab project.



**Figure 3** - Project properties window showing target connection settings.

Note that the “Auto Program” and “Load into SRAM” boxes are checked. Click “OK” when your selections are complete. You may want to save your project at this point.

## 3.3 Running the GUI


This section will outline how to run the GUI including how to set up hardware, launch the GUI, and interact with the application variables.

### 3.3.1 GUI connection

With the DC bus powered, connect a USB cable from the PC to the controlCARD or LaunchPad.

If using the high voltage kit, proceed with connecting to the target before energizing the high voltage AC input (110-220Vac) or high voltage DC Bus (50-350Vdc).

You can verify the connection to your emulator by checking the Windows Device Manager.



**Figure 4** - Windows Device Manager showing both an XDS100 and an XDS110 connected.

### 3.3.2 Launching the GUI

To launch the GUI, hit the Run button (the triangular icon) in GUI Composer. A new tab should open, showing the Universal GUI and a README window. Close the README once you have read it. If you need to see it again, you can access it under the "Help" menu.

The GUI will automatically connect to your device and load the application. You can track its progress by reading the status bar at the bottom. When it is connected and running, you should see "Connected to target. Hardware Connected." in the status bar, and signs that the application is executing (e.g. a blinking LED on the board, a valid number of pole pairs displayed in the GUI).

# TI Spins Motors



If you need to disconnect/reconnect to the GUI, there is a button to toggle connection status in the lower left corner. If you need to reload the program or if it didn't auto-load upon connecting, there is a "Program Device..." selection under the "File" menu.

## 3.3.3 GUI overview

The first tab displayed in the GUI is the InstaSPIN-FOC Instrumentation tab. It provides instrumentation for the InstaSPIN-FOC labs, focused on the motorVars, and userParams structures. Use the InstaSPIN-FOC lab guide for more information on the items displayed and how to interact with them for each of the labs.

**C2000™ InstaSPIN Universal GUI** | File Edit Help

InstaSPIN-FOC | DRV8320RS SPI

### InstaSPIN-FOC™ Instrumentation

☐ Enable System ☐ RsRecalc ☐ MTPA ☐ user.h Params ☐ OffsetCalc ☐ Field-weakening ☐ Run ☐ ForceAngle ☐ PowerWarp (EPL)

☒ Motor Identified

MOTOR\_TYPE\_INDUCTION | EST\_TRAJ\_STATE\_ERROR | Pole Pairs: 0 | EST\_STATE\_ERROR

Rs (Ohm): 0.0000 | Rs (Ohm) Online: 0.0000  
Ls-d (mH): 0.0000 | Ls-q (mH): 0.0000  
Flux (V/Hz): 0.0000 | Rr (Ohm): 0.0000  
Max Current for R est (A): 0.0000 | Max Current for L est (A): 0.0000  
Magnetizing Current (A): 0.0000

Bus Voltage (V): 0

speedRef (Hz): 0.000 | torque (N-m): 0.00000 | V.0: 0.00000000 | I.0: 0.00000000 | CPU Frequency (MHz): 0  
acceleration Max (Hz/s): 0.000 | RsOnline Current (A): 0.000 | V.1: 0.00000000 | I.1: 0.00000000 | PWM Frequency (kHz): 0  
speedTraj (Hz): 0.000 | Iq\_Ref (A): 0.000 | V.2: 0.00000000 | I.2: 0.00000000 | ADC Sampling (kHz): 0  
speed (Hz): 0.000 | Id\_Ref (A): 0.000 | Vs (V): 0.000 | Is (A): 0.000 | Current Controller (kHz): 0  
Speed Error (Hz): 0.00 | 0.00 % | Id\_Kp: 0.000 | Vq (V): 0.000 | Iq (A): 0.000 | FAST™ Frequency (kHz): 0  
Kp\_spd: 0.000 | Id\_Ki: 0.000 | Vd (V): 0.000 | Id (A): 0.000 | Speed Controller (kHz): 0  
Ki\_spd: 0.000 | Iq\_Kp: 0.000 | Current Sensors: 0 | Trajectory Frequency (kHz): 0  
Iq\_Ki: 0.000 | Force Angle +/- (Hz): 0.00  
Force Angle +/- (RPM): 0  
ADC Scale Voltage (V): 0.000  
ADC Scale Current (A): 0.000  
Max Current (A): 0.000

Connected to TI Cloud Agent. | Powered By GUI Composer™ | TEXAS INSTRUMENTS

Figure 5 – InstaSPIN-FOC instrumentation tab.

# TI Spins Motors



The next tab is provided to view and modify the configurations of the DRV8320RS gate driver if necessary. This tab only applies to the BOOSTXL-DRV8320RS and can be ignored if not in use.

Figure 6 – DRV8320RS Registers tab.

## 3.3.4 Motor ID lab example

This section will walk through running the InstaSPIN Motor ID lab (lab 05) on a LAUNCHXL-F280049C with a BOOSTXL-DRV8320RS. The motor used for the demo is an Anaheim Automation BLY172S-24V-4000. The hardware was set up as described in the readme and hardware guide documents.

Following the instructions in the InstaSPIN-FOC lab guide, the *is05\_motor\_id* lab was imported into CCSv8, the user.h was updated to reflect the motor, and the Flash\_Lib configuration was built.

# TI Spins Motors




Figure 7 - CCS workspace showing motor ID lab project.

Opening the C2000Ware\_MotorControlSDK\_InstaSPIN\_GUI project properties in GUI Composer as described earlier in this document, the new .out was added to the project and the Device and Connection were confirmed to be correct for the board being used.




Figure 8 - GUI Composer project properties for motor ID lab on LAUNCHXL-F280049C with a BOOSTXL-DRV8320RS. Note this is also the default configuration.


After clicking “OK” and saving the application, the application was launched in the browser by hitting the run button. Once the application was loaded and running (LED on LaunchPad could be observed blinking), the motor identification instructions from the lab guide could be followed.



# TI Spins Motors



This started with checking the “Enable System” checkbox (setting `motorVars.flagEnableSys`) and then checking the “Run” checkbox (setting `motorVars.flagRunIdentAndOnLine`). Once motor identification ran and completed, the “Run” checkbox was automatically unchecked and the “Motor Identified” status indicator was set.



**Figure 9** – GUI showing the status of variables after running the motor identification lab.

The newly defined motor parameters could be noted in the GUI and recorded to update the `user.h`. To run the motor, the “Run” checkbox was checked again. At this point you can try changing the `speedRef_Hz` or the `accelerationMax_Hzps` values and observing their effects. When finished, the “Run” box was unchecked to disable the PWM output, and the GUI window could be closed.

## 4 Next steps

For next steps, you can continue to try the GUI with different InstaSPIN labs, following the lab guide instructions. Note that not all lab projects may be compatible with the GUI. For example, at this time the GUI does not support the dual motor lab (lab 11).

When the GUI is configured to your liking, you may want to consider exporting it as a standalone application so that it can be run offline by going to “File”->“Export”->“As Stand-Alone App” in GUI Composer and following the directions for your OS. Other customizations can be made to the GUI as well. Use the “Help” menu in GUI Composer to help you get started.

## 5 Support

For questions about InstaSPIN-FOC, the MotorControl SDK, and the InstaSPIN Universal GUI, visit the [C2000 microcontrollers forum](#) in the TI E2E Community. For general GUI Composer issues, visit the [Code Composer Studio™](#) forum.